


How to Connect to the Gemini Wirelessly

HT21700001


OS: Windows Vista

Keywords: connect, Gemini, wireless, wirelessly, writer, blue, tooth, bluetooth


1. Double-click the **BlueSoleil** icon on your desktop. Bluetooth will start. Double-click the **BlueSoleil** icon again to open the program.




2. Double-click the **Gemini** icon.




3. Left-click the **Serial Port Services** icon. You Gemini is ready to write.




4. To determine the Com port, right-click the **Gemini** icon. Left-click **Status**.



5. Look at **COM Port** to determine which Com port number.



6. Click on **OK** when finished.



7. **Minimize** the BlueSoleil program. Start your CAT software. Ensure you are set up for the Com port listed earlier.

